

**Stäubli C programming interface
for low level robot control
s6.6.5**

Table of content

I. Overview.....	3
a. <i>Programming interface</i>	3
b. <i>Dynamic architecture</i>	3
II. Construction / destruction	4
a. <i>LLI_construct</i>	4
b. <i>LLI_constructKinOnly</i>	4
c. <i>LLI_destroy</i>	4
III. System programming interface	5
a. <i>LLI_state</i>	5
b. <i>LLI_ioctl (configuration)</i>	5
c. <i>Error management (LLI_plugEventFunc)</i>	6
d. <i>IO functions</i>	6
e. <i>Recorder functions</i>	7
IV. Control programming interface	8
a. <i>LLI_init</i>	8
b. <i>LLI_enable</i>	8
c. <i>LLI_disable</i>	8
d. <i>LLI_get</i>	8
e. <i>LLI_set</i>	8
V. Kinematics programming interface	10
a. <i>LLI_reverseKine</i>	10
b. <i>LLI_forwardKine</i>	10

I. Overview

a. Programming interface

This document describes the C programming interface for low level robot control; the library header is fully defined with the file `lli_lowlevelinterf.h`.

Each function uses a `LLI_RobotId` parameter (created with `LLI_construct`) and return a `LLI_Status` to report if the function was completed correctly.

The programming interface is described in this document in four sections:

- Construction / destruction (library management)
- System programming interface (system parameters and state)
- Control programming interface (robot control functions)
- Kinematics programming interface (kinematics functions)

b. Dynamic architecture

The use of the LLI library for robot control requires:

- an interrupt function, called by a hardware-generated clock, and synchronized with the drive control (see `LLI_construct`)
- a synchronous task, synchronized with the interrupt function, to control the robot (see `LLI_get` and `LLI_set`). The synchronous task must have the priority given by the `LLI_ioctl` command (`LLI_GET_SYNCHRO_TASK_PRIORITY`).
- some asynchronous tasks, to initialize and configure the system. The asynchronous task must have a lower priority than the synchronous task (a higher value for the VxWorks priority parameter).

This specification details which functions must be used in a synchronous context or asynchronous context, and which instruction can be used in both contexts.

II. Construction / destruction

Each constructor can be used to specify the sys, usr and log directories to be used by LLI. If NULL, the corresponding partitions of the flash disk are used. It can be used to boot on a USB key (see readme - Developments).

Construction errors are stored in a file (see Error management (LLI_pluginEventFunc)).

a. LLI_construct

This constructor gives access to control and kinematics programming interface (refer to Control programming interface and Kinematics programming interface).

LLI_construct creates and configures the (static) software modules of the library, but performs no dynamic initialization that must be done later with LLI_init.

The first parameter defines a function to be called in the context of the Sercos (CS8) or Starc (CS8C) system interrupt. It should not be called from anywhere else:

- it is called at the end of the interrupt, after commands are sent to the drives.
- the code for this function must be very short and valid in the context of the interrupt (for example, no wait on semaphores, etc...).

Typically, this function will just release a binary semaphore on which is suspended the synchronous task (see test program). When the synchronous task takes this semaphore, it must call the LLI_get, then the LLI_set functions.

b. LLI_constructKinOnly

This constructor gives access to the kinematics programming interface only (refer to Kinematics programming interface).

c. LLI_destroy

- All dynamic memory is freed.
- Robot is in a stable safe state after destruction.
- It is possible to reconstruct the robot interface after proper destruction.

III. System programming interface

The following functions can be used whatever the constructor previously called.

a. LLI_state

LLI_state returns the current state, which contains the following information:

- initialized / not initialized / no license
- enabled / enabling / disabling / disabled
- calibrated / not calibrated / calibrating
- settled / not settled (i.e. robot position stabilized)
- emergency stop / no emergency stop

LLI_state can be called in both synchronous and asynchronous contexts.

b. LLI_ioctl (configuration)

The function LLI_ioctl reads or modifies the system configuration; it can be called in both synchronous and asynchronous contexts, or only in asynchronous context, depending on the parameter:

Parameter	Set
LLI_GET_SOFTWARE_VERSION	Return the LLI library version (LLI_SoftwareVersion)
LLI_GET_ROBOT_TYPE	Return the robot type (LLI_robotType)
LLI_GET_JNT_NUMBER	Return the number of robot joints (unsigned int)
LLI_SET_USER_MARKS	(asynchronous context only) Set and store a new value of the user mark (double[])
LLI_GET_USER_MARKS	Get the value of the user mark position (double[]). In factory setting, this position corresponds to the physical mark on the joints
LLI_GET_JNT_RANGE	Get the arm software joints limits: maximum and minimum values (LLI_JointRange[]).
LLI_RECOVER_ABS_JNT_POS	(CS8 controller / asynchronous context only) Restore correct calibration parameters in the calibration board (DAPS). The robot must be near the position (double[]) passed to the function ($\pm 1/2$ motor turn on each joint).
LLI_SET_ABS_JNT_POS	(asynchronous context only) Change the position (double[]) of each axis to match the position passed to the function. The new zero position of each axis is stored in the system configuration file arm.cfx.
LLI_GET_CYCLE_TIME	Get the time (double, in s) between two robot interrupts.
LLI_GET_SYNCHRO_TASK_PRIORITY	Get the VxWorks task priority (integer) to apply to the synchronous task.

Parameter	Set
LLI_SET_TORQUE_MODE	(asynchronous context only) Switch the specified axis (unsigned int) from the standard position control to the torque control mode. If the specified parameter is NULL, the switch is done on all axes.
LLI_SET_POS_VEL_MODE	(asynchronous context only) Switch the specified axis (unsigned int) from the torque control mode to the standard position control. If the specified parameter is NULL, the switch is done on all axes.
LLI_SET_TUNING	(asynchronous context only) Send a command to the drives to change arm tuning parameters. Arm power must be off.

c. Error management (LLI_plugEventFunc)

The controller outputs errors on its serial port COM1, (115200, 8 bits, no parity, 1 stop bit, VT100 emulation). Errors are also logged in file named error.log on the /log flash disk partition. Errors can be also redirected to the user using the function LLI_plugEventFunc:

- This function plugs a user function that is called with each new system event.
- The parameter of the user function is pointer to the string that contains the event description

LLI_plugEventFunc can be called in both synchronous and asynchronous contexts.

d. IO functions

An IO is referenced by its name; LLI_getDinId and LLI_getDoutId convert this name into an id that is then used by LLI_readDio or LLI_writeDout for a fast IO access.

- LLI_getDinId returns an ID on a Digital Input, the entry parameter is the name of Din as defined in the robot controller (asynchronous context only)
- LLI_getDoutId returns an ID on a Digital Output, the entry parameter is the name of Dout (asynchronous context only)
- LLI_readDio returns the value of the IO (input or output): 0, 1 or undefined
- LLI_writeDout sets the output to 1 or 0

LLI_getDinId and LLI_getDoutId must be called in asynchronous context only; LLI_readDio and LLI_writeDout can be called in both synchronous and asynchronous contexts.

e. Recorder functions

The system recorder records traces of the system state (command, feedback, IOs, ...) in a synchronous task. The data to record, and some recording parameters, are specified in a system configuration file (by default /usr/recorder/record.cfx).

- LLI_recInit() configures the system recorder with the specified configuration file
- LLI_recStart() starts the record defined with LLI_recInit
- LLI_recStop() stops the record started with LLI_recStart
- LLI_recStore() stores to the specified location the record completed with LLI_recStop

LLI_recInit and LLI_recStore must be called in asynchronous context only; LLI_recStart and LLI_recStop can be called in both synchronous and asynchronous contexts.

IV. Control programming interface

The following functions can be used after the constructor LLI_construct has been called.

a. LLI_init

LLI_init performs the dynamic initialization of the LLI library and completes the initialization started with LLI_construct:

- hardware is initialized : Sercos (CS8) / Starc (CS8C) communication with drives
- robot is calibrated.

LLI_init must be called in asynchronous context only.

b. LLI_enable

LLI_enable sends a request to start the arm power enabling sequence; the enabling sequence is started with the next call of the LLI_set function. An error is raised if the enabling sequence cannot be completed.

- The enabling sequence can be aborted at any time with the LLI_disable function
- The enabling sequence can be tracked with the LLI_state function

LLI_enable can be called in both synchronous and asynchronous contexts.

c. LLI_disable

LLI_disable sends a request to start the arm power disabling sequence; the disabling sequence is started with the next call of the LLI_set function.

- The disabling sequence aborts the pending enabling sequence, if any, without error message.
- The disabling sequence can be tracked with the LLI_state function.

LLI_disable can be called in both synchronous and asynchronous contexts.

d. LLI_get

LLI_get updates the system state by reading feedback from the drives. The refreshed state can then be read with the LLI_state function.

LLI_get must be called before LLI_set, at each synchronous cycle.

e. LLI_set

LLI_set updates the system state by sending a new command to the drives. An error is raised if invalid commands are detected (position, velocity, delta position or delta velocity out of range); arm power is then automatically disabled.

- The velocity command is supposed to be the instantaneous derivative of the position command. Position and velocity are micro-interpolated in the drives, to allow the servo loop to run at higher rates.

- Each drive contains a position, a velocity loop, and a current loop. External velocity and torque feedforwards may be added to improve the control, especially to compensate for the joint couplings.
- When torque mode is activated (see LLI_ioctrl (configuration)), the position and velocity control loops are disabled. Then, the torque feedforward is used as the torque command. In this mode, the measured position and velocity should be fed back as commands. They are not used in the control loops, but they are still checked by the system, which provides a minimal safety level.

LLI_set must be called after LLI_get at each synchronous cycle.

V. Kinematics programming interface

The following functions can be used after the constructor `LLI_construct` or `LLI_constructKinOnly` has been called.

a. `LLI_reverseKine`

The `LLI_reverseKine` function computes a joint position corresponding to a specified Cartesian position and robot configuration. The Cartesian position is the position of the robot flange referenced to the base of the robot.

- The reference joint position and joint limits are used when several solutions can be found: the result is then the nearest joint position within the joint limits.
- The function returns a diagnostic when the computation has no solution.

`LLI_reverseKine` can be called in both synchronous and asynchronous contexts.

b. `LLI_forwardKine`

The `LLI_forwardKine` function returns the Cartesian position of the robot flange, and the robot configuration corresponding to a specified joint position.

`LLI_forwardKine` can be called in both synchronous and asynchronous contexts.